




Well-preserved

By Patti Carey of Patti's Patchwork
for *Quilt Block Mania* September 2026



Finished Size: 12" square (12½" edge-to-edge)


Skill level: Confident beginner

Fabrics used: Toscana texture by Northcott

Fabric	Cutting Instructions
A –background (#9020- 97 graphite)	◇ Cut (1) 2½" square (A7), (2) 5" x 1½" pieces (A6), (2) 5½" x 1" pieces (A4), (2) 5" x 1" pieces (A5), (8) 2" x 1" pieces (A1), (8) 1½" squares (A3) and (8) 1" squares (A2)
B – shelves (#9020-35 nutmeg)	◇ Cut (2) 1" x 7½" pieces (B1) and (2) 1" x 5½" pieces (B2)
C -jar lids (#9020-93)	◇ Cut (2) 1" x 2½" pieces (C1) and (2) 1" x 3" pieces (C2)
D – tall jars (#9020-231 valentino)	◇ Cut (2) 7" x 5½" pieces (D)
E & F – short jars (#9020-520 sunflower & 571 monarch)	◇ From each fabric, cut (1) 6½" x 4½" piece (E & F)

General Piecing: All seams are ¼" unless noted. Press seams toward darker fabric unless indicated.



1. Sew an A1 piece to each short end of each C1 and C2 piece as shown; press seam toward B.




2. Lay an A2 in each corner of (1) D piece and the F piece; sew diagonally from corner to corner on each A1 square, trim ¼" from seam and press seam toward D/F.



3. Repeat step 2 with the remaining D piece and the E piece, using the A3 squares.



4. Sew a C1/A unit to short end of each D unit and a C2/A unit to long edge of E and F units; press seam toward D/E/F.



5. Sew a B2 to remaining short edge of each D unit; press seam toward B. Add an A4 piece to lid edge of small-corner D unit. Add an A4 piece to B edge of large-corner D unit. Press seam toward unit.


6. Sew an A5 to right edge of E unit and an A6 to left edge; press seams toward E, then add a B1 piece to bottom edge, pressing toward B.

7. Sew an A5 to left edge of F unit and an A6 to right edge; press seams toward F, then add a B1 piece to bottom edge, pressing toward B.



8. Arrange the D, E and F units in a “square” as shown, placing the A7 square in the center space. Aligning A7 with the bottom right corner of the small-corner D unit, sew the first 1½” of the vertical seam as indicated by the * arrow in the diagram, finger-pressing seam toward D unit.

9. Add top of the F unit to the D/A7 edge, pressing seam toward D, then add the large-corner D unit to the F/A7 edge (press seam toward D), then add the E unit to top of D/A7 (press seam toward E). Finally, finish the vertical seam by sewing the left edge of E unit to right edge of upper D unit.



If you like this pattern you'll love all the great patterns at www.pattispatchwork.com – home of the awesome [E-Z Miter/Lone Star Tool](#) and quilt patterns using time-saving efficient methods. [Sign up](#) for the monthly newsletter for quilty goodness and subscriber-only specials. Also **subscribe** to Patti's monthly blog at www.pattispatchwork-blog.com for quilting tips and tasty recipes.